

Want Help?

Contact 1-888-dVUENOW or support@dopplerVUE.com. We'll step you through the install process or answer any questions.



Install dopplerVUE for a 30-Day Free Trial

Step 1: Download dopplerVUE

Download the dopplerVUE setup file. To run dopplerVUE you will need at least 6 GB of free disk space, 1 GB of memory, and a 2.0 GHz processor.

Step 2: Check Windows Components

Windows Vista Users

Enable IIS 6 Compatibility and MSMQ:

1. Open the Control Panel and click **Programs and Features**.
2. Under Tasks, click **Turn Windows Features on or off**.
3. Expand **Internet Information Services > Web Management Tools**.
4. Expand **IIS 6 Management Compatibility** and select **IIS Metabase and IIS 6 configuration compatibility**.
5. Under **Web Management Tools**, select the following features:
 - **IIS Management Console**
 - **IIS Management Scripts and Tools**
 - **IIS Management Service**
6. Expand **Microsoft Message Queue (MSMQ) Server > Microsoft Message Queue (MSMQ) Server Core** and select the following features:
 - **MSMQ Active Directory Domain Services Integration**
 - **Multicasting Support**
7. Under **Microsoft Message Queue (MSMQ) Server**, select **MSMQ DCOM Proxy**.
8. Click **OK**.

Windows XP Professional Users

Verify .NET Framework 2.0 is installed:

1. On the task bar, click **Start > Control Panel**.
2. Open **Add or Remove Programs**.
3. Scroll down the list of installed program and make sure Microsoft .NET Framework 2.0 is installed.
4. If .NET Framework 2.0 is not installed, see the Microsoft Web site for instructions on how to obtain and install .NET Framework 2.0.

Enable IIS 6 and MSMQ:

1. On the task bar, click **Start > Control Panel**.
2. Open **Add or Remove Programs**.
3. Click **Add/Remove Windows Components**.
4. In the Components list, select **Internet Information Services (IIS)** and **Message Queuing**.
5. Click **Next**, then click **Finish**.

Verify Internet Explorer is installed:

1. On the task bar, click **Start > Programs > Internet Explorer**.
2. If Internet Explorer 7 is not installed, see the Microsoft Web site for instructions on how to obtain and install Internet Explorer 7. Note: Internet Explorer 6 is supported, but it is recommended you install Internet Explorer 7.

Step 3: Install dopplerVUE

Launch the setup.exe file downloaded in Step 1 and follow the onscreen instructions. See the dopplerVUE Installation Guide for additional information.